

System Calls


Contents

- A high-level view of System Calls
 - Mostly from the user's perspective
 - From textbook (section 1.6)
- A look at the R3000
 - A brief overview
 - Mostly focused on exception handling
 - From "Hardware Guide" on class web site
 - Allow me to provide "real" examples of theory
- System Call implementation
 - Case Study: OS/161 system call handling

Operating System System Calls

Kernel Level

User Level



System Calls

- Can be viewed as special procedure calls
 - Provides for a controlled entry into the kernel
 - While in kernel, they perform a privileged operation
 - Returns to original caller with the result
- The system call interface represents the abstract machine provided by the operating system.

A Brief Overview of Classes System Calls

- From the user's perspective
 - Process Management
 - File I/O
 - Directories management
 - Some other selected Calls
 - There are many more
 - On Linux, see `man syscalls` for a list

Some System Calls For Process Management

Process management	
Call	Description
<code>pid = fork()</code>	Create a child process identical to the parent
<code>pid = waitpid(pid, &statloc, options)</code>	Wait for a child to terminate
<code>s = execve(name, argv, environp)</code>	Replace a process' core image
<code>exit(status)</code>	Terminate process execution and return status

Some System Calls For File Management

File management	
Call	Description
fd = open(file, how, ...)	Open a file for reading, writing or both
s = close(fd)	Close an open file
n = read(fd, buffer, nbytes)	Read data from a file into a buffer
n = write(fd, buffer, nbytes)	Write data from a buffer into a file
position = lseek(fd, offset, whence)	Move the file pointer
s = stat(name, &buf)	Get a file's status information

Some System Calls For Directory Management

Directory and file system management	
Call	Description
s = mkdir(name, mode)	Create a new directory
s = rmdir(name)	Remove an empty directory
s = link(name1, name2)	Create a new entry, name2, pointing to name1
s = unlink(name)	Remove a directory entry
s = mount(special, name, flag)	Mount a file system
s = umount(special)	Unmount a file system

Some System Calls For Miscellaneous Tasks

Miscellaneous	
Call	Description
s = chdir(dirname)	Change the working directory
s = chmod(name, mode)	Change a file's protection bits
s = kill(pid, signal)	Send a signal to a process
seconds = time(&seconds)	Get the elapsed time since Jan. 1, 1970

System Calls

- A stripped down shell:

```

while (TRUE) {
    type_prompt( );
    read_command (command, parameters)
}

if (fork() != 0) {
    /* Parent code */
    waitpid( -1, &status, 0);
} else {
    /* Child code */
    execve (command, parameters, 0);
}
    
```

System Calls

UNIX	Win32	Description
fork	CreateProcess	Create a new process
waitpid	WaitForSingleObject	Can wait for a process to exit
execve	(none)	CreateProcess + fork + execve
exit	ExitProcess	Terminate execution
open	CreateFile	Create a file or open an existing file
close	CloseHandle	Close a file
read	ReadFile	Read data from a file
write	WriteFile	Write data to a file
lseek	SetFilePointer	Move the file pointer
stat	GetFileAttributesEx	Get various file attributes
mkdir	CreateDirectory	Create a new directory
rmdir	RemoveDirectory	Remove an empty directory
link	(none)	Win32 does not support links
unlink	DeleteFile	Destroy an existing file
mount	(none)	Win32 does not support mount
umount	(none)	Win32 does not support mount
chdir	SetCurrentDirectory	Change the current working directory
chmod	(none)	Win32 does not support security (although NT does)
kill	(none)	Win32 does not support signals
time	GetLocalTime	Get the current time

The MIPS R2000/R3000

- Before looking at system call mechanics in some detail, we need a basic understanding of the MIPS R3000

MIPS R3000

- RISC architecture – 5 stage pipeline




Figure 1.1. MIPS 5 stage pipeline

MIPS R3000

- Load/store architecture
 - No instructions that operate on memory except load and store
 - Simple load/stores to/from memory from/to registers
 - Store word: `sw r4, (r5)`
 - Store contents of r4 in memory using address contained in register r5
 - Load word: `lw r3, (r7)`
 - Load contents of memory into r3 using address contained in r7
 - Delay of one instruction after load before data available in destination register
 - Must always an instruction between a load from memory and the subsequent use of the register.
- `lw, sw, lb, sb, lh, sh, ...`

MIPS R3000


- Arithmetic and logical operations are register to register operations
 - E.g., `add r3, r2, r1`
 - No arithmetic operations on memory
- Example
 - `add r3, r2, r1` ⇒ $r3 = r2 + r1$
- Some other instructions
 - `add, sub, and, or, xor, sll, srl`

MIPS R3000

- All instructions are encoded in 32-bit
- Some instructions have *immediate* operands
 - Immediate values are constants encoded in the instruction itself
 - Only 16-bit value
 - Examples
 - Add Immediate: `addi r2, r1, 2048`
 - ⇒ $r2 = r1 + 2048$
 - Load Immediate: `li r2, 1234`
 - ⇒ $r2 = 1234$

MIPS Registers

- User-mode accessible registers
 - 32 general purpose registers
 - r0 hardwired to zero
 - r31 the *link* register for jump-and-link (JAL) instruction
 - HI/LO
 - 2 * 32-bits for multiply and divide
 - PC
 - Not directly visible
 - Modified implicitly by jump and branch instructions



Branching and Jumping


- Branching and jumping have a *branch delay slot*
 - The instruction following a branch or jump is always executed

```

sw $0, ($3)
j 1f
li $2, 1
:
1: sw $2, ($3)
    
```

Jump and Link

- JAL is used to implement function calls
 - r31 = PC+8
- Jump Register (JR) is used to return from function call




COMP3231 04s1

19

R3000 Address Space Layout

- kuseg:
 - 2 gigabytes
 - TLB translated (mapped)
 - Cacheable
 - user-mode and kernel mode accessible
 - Page size is 4K




COMP3231 04s1

0x00000000

R3000 Address Space Layout

- kseg0:
 - 512 megabytes
 - Fixed translation window to physical memory
 - 0x80000000 - 0x9fffffff virtual = 0x00000000 - 0x1ffffff physical
 - Cacheable
 - Only kernel-mode accessible
 - Usually where the kernel code is placed




COMP3231 04s1

0x00000000

R3000 Address Space Layout

- kseg1:
 - 512 megabytes
 - Fixed translation window to physical memory
 - 0xA0000000 - 0xbffffff virtual = 0x00000000 - 0x1ffffff physical
 - **NOT** cacheable
 - Only kernel-mode accessible
 - Where devices are accessed (and boot ROM)




COMP3231 04s1

0x00000000

R3000 Address Space Layout

- kseg2:
 - 1024 megabytes
 - TLB translated (mapped)
 - Cacheable
 - Only kernel-mode accessible



COMP3231 04s1

0x00000000

System161 Aside

- System/161 simulates an R3000 without a cache.
 - You don't need to worry about cache issues with programming OS161 running on System/161



COMP3231 04s1

24

Coprocessor 0

- The processor control registers are located in CP0
 - Exception management registers
 - Translation management registers
- CP0 is manipulated using `mtc0` (move to) and `mfc0` (move from) instructions
 - `mtc0/mfc0` are only accessible in kernel mode.

CP0 Registers

- Exception Management
 - `c0_cause`
 - Cause of the recent exception
 - `c0_status`
 - Current status of the CPU
 - `c0_epc`
 - Address of the instruction that caused the exception
 - Note the BD bit in `c0_cause`
 - `c0_badvaddr`
 - Address accessed that caused the exception
 - Miscellaneous
 - `c0_prid`
 - Processor Identifier
 - Memory Management
 - `c0_index`
 - `c0_random`
 - `c0_entryhi`
 - `c0_entrylo`
 - `c0_context`
- More about these later in course

c0_status




Figure 3.2. Fields in status register (SR)

- CU0-3
 - Enable access to coprocessors (1 = enable)
 - CU0 never enabled for user mode
 - Always accessible in kernel-mode regardless of setting
 - CU1 is floating point unit (if present, FPU not in sys161)
 - CU2-3 reserved

c0_status




Figure 3.2. Fields in status register (SR)

- RE
 - Reverse endian
- BEV
 - Boot exception vectors
 - 1 = use ROM exception vectors
 - 0 = use RAM exception vectors
- TS
 - TLB shutdown (1 = duplicate entry, need a hardware reset)

c0_status




Figure 3.2. Fields in status register (SR)

- PE
 - Parity error in cache
- CM
 - Cache management
- PZ
 - Cache parity zero
- SwC
 - Access instruction cache as data
- IsC
 - Isolate data cache
- For practical purposes, you can ignore these bits

c0_status




Figure 3.2. Fields in status register (SR)

- IM
 - Individual interrupt mask bits
 - 6 external
 - 2 software
- KU
 - 0 = kernel
 - 1 = user mode
- IE
 - 0 = all interrupts masked
 - 1 = interrupts enable
 - Mask determined via IM bits
- c, p, o = current, previous, old

c0_cause

31
30
29
28
27
16
15
8
7
6
2
1
0

BD	0	CE	0	IP	0	ExcCode	0
----	---	----	---	----	---	---------	---

Figure 3.3. Fields in the Cause register

- **BD**
 - If set, the instruction that caused the exception was in a branch delay slot
- **CE**
 - Coprocessor error
 - Attempt to access disabled Copro.
- **IP**
 - Interrupts pending
 - 8 bits indicating current state of interrupt lines
- **ExcCode**
 - The code number of the exception taken

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
31

Exception Codes

ExcCode Value	Mnemonic	Description
0	Int	Interrupt
1	Mod	"TLB modification"
2	TLBL	"TLB load/TLB store"
3	TLBS	
4	AdEL	Address error (on load/I-fetch or store respectively). Either an attempt to access outside kuseg when in user mode, or an attempt to read a word or half-word at a misaligned address.
5	AdES	

Table 3.2. ExcCode values: different kinds of exceptions

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
32

Exception Codes

ExcCode Value	Mnemonic	Description
6	IBE	Bus error (instruction fetch or data load, respectively). External hardware has signalled an error of some kind; proper exception handling is system-dependent. The R30xx family CPUs can't take a bus error on a store; the write buffer would make such an exception "imprecise".
7	DBE	
8	Syscall	Generated unconditionally by a <i>syscall</i> instruction.
9	Bp	Breakpoint - a <i>break</i> instruction.
10	RI	"reserved instruction"
11	CpU	"Co-Processor unusable"
12	Ov	"arithmetic overflow". Note that "unsigned" versions of instructions (e.g. <i>addu</i>) never cause this exception.
13-31	-	reserved. Some are already defined for MIPS CPUs such as the R6000 and R4xxx

Table 3.2. ExcCode values: different kinds of exceptions

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
33

c0_epc

- **The Exception Program Counter**
 - The address of where to restart execution after handling the exception or interrupt
 - BD-bit in *c0_cause* is used on rare occasions when one needs to identify the actual exception-causing instruction
 - Example
 - Assume `sw r3, (r4)` causes a page fault exception

```

nop
sw r3 (r4)
nop

```

c0_epc
BD = 0

```

nop
j printf
sw r3 (r4)
nop

```

c0_epc
BD = 1

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
34

c0_badvaddr

- The address access that caused the exception
 - Set if exception is
 - MMU related
 - Access to kernel space from user-mode
 - Unaligned memory access
 - 4-byte words must be aligned on a 4-byte boundary

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
35


Exception Vectors

Program address	"segment"	Physical Address	Description
0x8000 0000	kseg0	0x0000 0000	TLB miss on <i>kuseg</i> reference only.
0x8000 0080	kseg0	0x0000 0080	All other exceptions.
0xbf00 0100	kseg1	0x1fe0 0100	Uncached alternative <i>kuseg</i> TLB miss entry point (used if <i>SR</i> bit BEV set).
0xbf00 0180	kseg1	0x1fe0 0180	Uncached alternative for all other exceptions, used if <i>SR</i> bit BEV set).
0xbf00 0000	kseg1	0x1fe0 0000	The "reset exception".

Table 4.1. Reset and exception entry points (vectors) for R30xx family

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
36

Hardware exception handling



- Let's now walk through an exception
 - Assume an interrupt occurred as the previous instruction completed
 - Note: We are in user mode with interrupts enabled



COMP3231 04s1

37

Labs

The labs are now:


- Thursday 4-5pm
- Friday 1-3pm
- In the "spoons" lab



COMP3231 04s1

38

Hardware exception handling




- Instruction address at which to restart after the interrupt is transferred to EPC



COMP3231 04s1

39


Hardware exception handling



COMP3231 04s1

40


Hardware exception handling



COMP3231 04s1

41


Hardware exception handling



COMP3231 04s1

42


Hardware exception handling




Returning from an exception

- For now, lets ignore
 - how the exception is actually handled
 - how user-level registers are preserved
- Let's simply look at how we return from the exception


Returning from an exception




Returning from an exception



Returning from an exception




Returning from an exception




Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().




Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().



Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().



Software Register Conventions


- Given 32 registers, which registers are used for
 - Local variables?
 - Argument passing?
 - Function call results?
 - Stack Pointer?

Software Register Conventions

Reg No	Name	Used for
0	zero	Always returns 0
1	at	(assembler temporary) Reserved for use by assembler
2-3	v0-v1	Value (except FP) returned by subroutine
4-7	a0-a3	(arguments) First four parameters for a subroutine
8-15	t0-t7	(temporaries) subroutines may use without saving
24-25	t8-t9	
16-23	s0-s7	Subroutine "register variables"; a subroutine which will write one of these must save the old value and restore it before it exits, so the calling routine sees their values preserved.
26-27	k0-k1	Reserved for use by interrupt/trap handler - may change under your feet
28	gp	global pointer - some runtime systems maintain this to give easy access to (some) "static" or "extern" variables.
29	sp	stack pointer
30	s8/tp	9th register variable. Subroutines which need one can use this as a "frame pointer".
31	ra	Return address for subroutine

Stack Frame

- MIPS calling convention for gcc
 - Args 1-4 have space reserved for them



Example Code

```
main ()                int sixargs(int a, int b,
{                      int c, int d, int e,
  int i;              int f)
                      {
  i =                  return a + b + c + d
  sixargs(1,2,3,4,5,6); + e + f;
}                      }
```

```
0040011c <main>:
40011c: 27bdfff8      addiu  sp,sp,-40
400120: afbf0024      sw    ra,36(sp)
400124: afbe0020      sw    s8,32(sp)
400128: 03a0f021      move  s8,sp
40012c: 24020005      li    v0,5
400130: afa20010      sw    v0,16(sp)
400134: 24020006      li    v0,6
400138: afa20014      sw    v0,20(sp)
40013c: 24040001      li    a0,1
400140: 24050002      li    a1,2
400144: 24060003      li    a2,3
400148: 0c10002c      jal   4000b0 <sixargs>
40014c: 24070004      li    a3,4
400150: afc20018      sw    v0,24(sp)
400154: 03c0e821      move  sp,s8
400158: 8fbf0024      lw    ra,36(sp)
40015c: 8fbe0020      lw    s8,32(sp)
400160: 03e00008      jr    ra
400164: 27bd0028      addiu  sp,sp,40
...
```

```
004000b0 <sixargs>:
4000b0: 27bdfff8      addiu  sp,sp,-8
4000b4: afbe0000      sw    s8,0(sp)
4000b8: 03a0f021      move  s8,sp
4000bc: afc40008      sw    a0,8(s8)
4000c0: afc5000c      sw    a1,12(s8)
4000c4: afc60010      sw    a2,16(s8)
4000c8: afc70014      sw    a3,20(s8)
4000cc: 8fc30008      lw    v1,8(s8)
4000d0: 8fc2000c      lw    v0,12(s8)
4000d4: 00000000      nop
4000d8: 00621021      addu  v0,v1,v0
4000dc: 8fc30010      lw    v1,16(s8)
4000e0: 00000000      nop
4000e4: 00431021      addu  v0,v0,v1
4000e8: 8fc30014      lw    v1,20(s8)
4000ec: 00000000      nop
4000f0: 00431021      addu  v0,v0,v1
4000f4: 8fc30018      lw    v1,24(s8)
4000f8: 00000000      nop
```

```
4000fc: 00431021      addu  v0,v0,v1
400100: 8fc3001c      lw    v1,28(s8)
400104: 00000000      nop
400108: 00431021      addu  v0,v0,v1
40010c: 03c0e821      move  sp,s8
400110: 8fbef000      lw    s8,0(sp)
400114: 03e00008      jr    ra
400118: 27bd0008      addiu  sp,sp,8
```

System Calls

Continued

User and Kernel Execution

- Simplistically, execution state consists of
 - Registers, processor mode, PC, SP
- User applications and the kernel have their own execution state.
- System call mechanism safely transfers from user execution to kernel execution and back.

System Call Mechanism in Principle

- Processor mode
 - Switched from user-mode to kernel-mode
 - Switched back when returning to user mode
- SP
 - User-level SP is saved and a kernel SP is initialised
 - User-level SP restored when returning to user-mode
- PC
 - User-level PC is saved and PC set to kernel entry point
 - User-level PC restored when returning to user-level
 - Kernel entry via the designated entry point must be strictly enforced


System Call Mechanism in Principle

- Registers
 - Set at user-level to indicate system call type and its arguments
 - A convention between applications and the kernel
 - Some registers are preserved at user-level or kernel-level in order to restart user-level execution
 - Depends on language calling convention etc.
 - Result of system call placed in registers when returning to user-level
 - Another convention

Why do we need system calls?

- Why not simply jump into the kernel via a function call????
 - Function calls do not
 - Change from user to kernel mode
 - and eventually back again
 - Restrict possible entry points to secure locations

Steps in Making a System Call



There are 11 steps in making the system call read (fd, buffer, nbytes)

MIPS System Calls

- System calls are invoked via a *syscall* instruction.
 - The *syscall* instruction causes an exception and transfers control to the general exception handler
 - A convention (an agreement between the kernel and applications) is required as to how user-level software indicates
 - Which system call is required
 - Where its arguments are
 - Where the result should go

OS/161 Systems Calls

- OS/161 uses the following conventions
 - Arguments are passed and returned via the normal C function calling convention
 - Additionally
 - Reg v0 contains the system call number
 - On return, reg a3 contains
 - 0: if success, v0 contains successful result
 - not 0: if failure, v0 has the errno.
 - » v0 stored in errno
 - » -1 returned in v0

CAUTION

- Seriously low-level code follows
- This code is not for the faint hearted

```

move    a0,s3
addi   a1,sp,16
jal    40068c <read>
li     a2,1024
move   s0,v0
blez   s0,400194 <docat+0x94>

```

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 67

User-Level System Call Walk Through

```

int read(int filehandle, void *buffer, size_t size)

```

- Three arguments, one return value
- Code fragment calling the read function

```

400124: 02602021  move a0,s3
400128: 27a50010  addiu a1,sp,16
40012c: 0c1001a3  jal 40068c <read>
400130: 24060400  li a2,1024
400134: 00408021  move s0,v0
400138: 1a000016  blez s0,400194 <docat+0x94>

```

- Args are loaded, return value is tested

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 68

The read() syscall function part 1

```

0040068c <read>:
40068c: 08100190  j 400640 <__syscall>
400690: 24020005  li v0,5

```

- Appropriate registers are preserved
 - Arguments (a0-a3), return address (ra), etc.
- The syscall number (5) is loaded into v0
- Jump (not jump and link) to the common syscall routine

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 69

The read() syscall function part 2

```

00400640 <__syscall>:
400640: 0000000c  syscall
400644: 10e00005  beqz a3,40065c <__syscall+0x1c>
400648: 00000000  nop
40064c: 3c011000  lui at,0x1000
400650: ac220000  sw v0,0(at)
400654: 2403ffff  li v1,-1
400658: 2402ffff  li v0,-1
40065c: 03e00008  jr ra
400660: 00000000  nop

```

Generate a syscall exception

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 70

The read() syscall function part 2

```

00400640 <__syscall>:
400640: 0000000c  syscall
400644: 10e00005  beqz a3,40065c <__syscall+0x1c>
400648: 00000000  nop
40064c: 3c011000  lui at,0x1000
400650: ac220000  sw v0,0(at)
400654: 2403ffff  li v1,-1
400658: 2402ffff  li v0,-1
40065c: 03e00008  jr ra
400660: 00000000  nop

```

Test success, if yes, branch to return from function

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 71

The read() syscall function part 2

```

00400640 <__syscall>:
400640: 0000000c  syscall
400644: 10e00005  beqz a3,40065c <__syscall+0x1c>
400648: 00000000  nop
40064c: 3c011000  lui at,0x1000
400650: ac220000  sw v0,0(at)
400654: 2403ffff  li v1,-1
400658: 2402ffff  li v0,-1
40065c: 03e00008  jr ra
400660: 00000000  nop

```

If failure, store code in errno

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 72

The read() syscall function part 2

```

00400640 <_syscall>:
400640: 0000000c syscall
400644: 10e00005 beqz a3,40065c
400648: 00000000 nop
40064c: 3c011000 lui at,0x1000
400650: ac220000 sw v0,0(at)
400654: 2403ffff li v1,-1
400658: 2402ffff li v0,-1
40065c: 03e00008 jr ra
400660: 00000000 nop
    
```

Set read() result to -1



COMP3231 04s1

73

The read() syscall function part 2

```

00400640 <_syscall>:
400640: 0000000c syscall
400644: 10e00005 beqz a3,40065c
400648: 00000000 nop
40064c: 3c011000 lui at,0x1000
400650: ac220000 sw v0,0(at)
400654: 2403ffff li v1,-1
400658: 2402ffff li v0,-1
40065c: 03e00008 jr ra
400660: 00000000 nop
    
```

Return to location after where read() was called



COMP3231 04s1

74

Summary

- From the caller's perspective, the read() system call behaves like a normal function call
 - It preserves the calling convention of the language
- However, the actual function implements its own convention by agreement with the kernel
 - Our OS/161 example assumes the kernel preserves appropriate registers(s0-s8, sp, gp, ra).
- Most languages have similar *support libraries* that interface with the operating system.



COMP3231 04s1

75

System Calls - Kernel Side

- Things left to do
 - Change to kernel stack
 - Preserve registers by saving to memory (the stack)
 - Leave saved registers somewhere accessible to
 - Read arguments
 - Store return values
 - Do the "read()"
 - Restore registers
 - Switch back to user stack
 - Return to application



COMP3231 04s1

76

```

exception:
    move k1, sp          /* Save previous stack pointer in k1 */
    mfc0 k0, c0_status  /* Get status register */
    andi k0, k0, CST_Kup /* Check the we-were-in-user-mode bit */
    beq k0, $0, 1f /* If clear, from kernel, already have stack */
    nop                 /* delay slot */

    /* Coming from user mode - load kernel stack into sp */
    la k0, curkstack    /* get address of "curkstack" */
    lw sp, 0(k0)        /* get its value */
    nop                 /* delay slot for the load */

1:
    mfc0 k0, c0_cause /* Now, load the exception cause. */
    j common_exception /* Skip to common code */
    nop                 /* delay slot */
    
```

Note k0, k1 registers available for kernel use



COMP3231 04s1

77

```

exception:
    move k1, sp          /* Save previous stack pointer in k1 */
    mfc0 k0, c0_status  /* Get status register */
    andi k0, k0, CST_Kup /* Check the we-were-in-user-mode bit */
    beq k0, $0, 1f /* If clear, from kernel, already have stack */
    nop                 /* delay slot */

    /* Coming from user mode - load kernel stack into sp */
    la k0, curkstack    /* get address of "curkstack" */
    lw sp, 0(k0)        /* get its value */
    nop                 /* delay slot for the load */

1:
    mfc0 k0, c0_cause /* Now, load the exception cause. */
    j common_exception /* Skip to common code */
    nop                 /* delay slot */
    
```



COMP3231 04s1

78

```

common_exception:
/*
 * At this point:
 *   Interrupts are off. (The processor did this for us.)
 *   k0 contains the exception cause value.
 *   k1 contains the old stack pointer.
 *   sp points into the kernel stack.
 *   All other registers are untouched.
 */

/*
 * Allocate stack space for 37 words to hold the trap frame,
 * plus four more words for a minimal argument block.
 */
addi sp, sp, -164

```

```

/* The order here must match mips/include/trapframe.h. */

sw ra, 160(sp) /* dummy for gdb */
sw s8, 156(sp) /* save s8 */
sw sp, 152(sp) /* dummy for gdb */
sw gp, 148(sp) /* save gp */
sw k1, 144(sp) /* dummy for gdb */
sw k0, 140(sp) /* dummy for gdb */

sw k1, 152(sp) /* real saved sp */
nop /* delay slot for store */

mfc0 k1, c0_epc /* Copr.0 reg 13 == PC for
sw k1, 160(sp) /* real saved PC */

```

These six stores are a "hack" to avoid confusing GDB. You can ignore the details of why and how.

```

/* The order here must match mips/include/trapframe.h. */

sw ra, 160(sp) /* dummy for gdb */
sw s8, 156(sp) /* save s8 */
sw sp, 152(sp) /* dummy for gdb */
sw gp, 148(sp) /* save gp */
sw k1, 144(sp) /* dummy for gdb */
sw k0, 140(sp) /* dummy for gdb */

sw k1, 152(sp) /* real saved sp */
nop /* delay slot for store */

mfc0 k1, c0_epc /* Copr.0 reg 13 == PC for exception */
sw k1, 160(sp) /* real saved PC */

```

The real work starts here

```

sw t9, 136(sp)
sw t8, 132(sp)
sw s7, 128(sp)
sw s6, 124(sp)
sw s5, 120(sp)
sw s4, 116(sp)
sw s3, 112(sp)
sw s2, 108(sp)
sw s1, 104(sp)
sw s0, 100(sp)
sw t7, 96(sp)
sw t6, 92(sp)
sw t5, 88(sp)
sw t4, 84(sp)
sw t3, 80(sp)
sw t2, 76(sp)
sw t1, 72(sp)
sw t0, 68(sp)
sw a3, 64(sp)
sw a2, 60(sp)
sw a1, 56(sp)
sw a0, 52(sp)
sw v1, 48(sp)
sw v0, 44(sp)
sw AT, 40(sp)
sw ra, 36(sp)

```

Save all the registers on the kernel stack

```

/*
 * Save special registers.
 */
mfhi t0
mflo t1
sw t0, 32(sp)
sw t1, 28(sp)

/*
 * Save remaining exception context information.
 */

sw k0, 24(sp) /* k0 was loaded with cause earlier */
mfc0 t1, c0_status /* Copr.0 reg 11 == status */
sw t1, 20(sp)
mfc0 t2, c0_vaddr /* Copr.0 reg 8 == faulting vaddr */
sw t2, 16(sp)

/*
 * Pretend to save $0 for gdb's benefit.
 */
sw $0, 12(sp)

```

We can now use the other registers (t0, t1) that we have preserved on the stack

```

/*
 * Prepare to call mips_trap(struct trapframe *)
 */

addiu a0, sp, 16 /* set argument */
jal mips_trap /* call it */
nop /* delay slot */

```

Create a pointer to the base of the saved registers and state in the first argument register

```

struct trapframe {
    u_int32_t tf_vaddr; /* vaddr register */
    u_int32_t tf_status; /* status register */
    u_int32_t tf_cause; /* cause register */
    u_int32_t tf_lo;
    u_int32_t tf_hi;
    u_int32_t tf_ra; /* Saved register 31 */
    u_int32_t tf_at; /* Saved register 1 (AT) */
    u_int32_t tf_v0; /* Saved register 2 (v0) */
    u_int32_t tf_v1; /* etc. */
    u_int32_t tf_a0;
    u_int32_t tf_a1;
    u_int32_t tf_a2;
    u_int32_t tf_a3;
    u_int32_t tf_t0;
    :
    u_int32_t tf_t7;
    u_int32_t tf_a0;
    :
    u_int32_t tf_s7;
    u_int32_t tf_t8;
    u_int32_t tf_t9;
    u_int32_t tf_k0; /* dummy (see exception.S comment) */
    u_int32_t tf_k1; /* dummy */
    u_int32_t tf_gp;
    u_int32_t tf_sp;
    u_int32_t tf_s8;
    u_int32_t tf_s9; /* coprocessor 0 epc register */
};

```

Kernel Stack

epc
s8
sp
gp
k1
k0
t9
t8
:
at
ra
hi
lo
cause
status
vaddr

By creating a pointer to here of type struct trapframe *, we can access the user's saved registers as normal variables within 'C'

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 85

Now we arrive in the 'C' kernel

```

/*
 * General trap (exception) handling function for mips.
 * This is called by the assembly-language exception handler once
 * the trapframe has been set up.
 */
void
mips_trap(struct trapframe *tf)
{
    u_int32_t code, isutlb, iskern;
    int savespl;

    /* The trap frame is supposed to be 37 registers long. */
    assert(sizeof(struct trapframe)==(37*4));

    /* Save the value of curspl, which belongs to the old context. */
    savespl = curspl;

    /* Right now, interrupts should be off. */
    curspl = SPL_HIGH;
}

```

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 86

What happens next?

- The kernel deals with whatever caused the exception
 - Syscall
 - Interrupt
 - Page fault
 - It potentially modifies the *trapframe*, etc
 - E.g., Store return code in v0, zero in a3
- 'mips_trap' eventually returns

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 87

```

exception_return:
/*
 * 16(sp)          no need to restore tf_vaddr */
lw t0, 20(sp)      /* load status register value into t0 */
nop               /* load delay slot */
mtc0 t0, c0_status /* store it back to coprocessor 0 */
/* 24(sp)          no need to restore tf_cause */

/* restore special registers */
lw t1, 28(sp)
lw t0, 32(sp)
mtlo t1
mthi t0

/* load the general registers */
lw ra, 36(sp)

lw AT, 40(sp)
lw v0, 44(sp)
lw v1, 48(sp)
lw a0, 52(sp)
lw a1, 56(sp)
lw a2, 60(sp)
lw a3, 64(sp)

```

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 88

```

lw t0, 68(sp)
lw t1, 72(sp)
lw t2, 76(sp)
lw t3, 80(sp)
lw t4, 84(sp)
lw t5, 88(sp)
lw t6, 92(sp)
lw t7, 96(sp)
lw s0, 100(sp)
lw s1, 104(sp)
lw s2, 108(sp)
lw s3, 112(sp)
lw s4, 116(sp)
lw s5, 120(sp)
lw s6, 124(sp)
lw s7, 128(sp)
lw t8, 132(sp)
lw t9, 136(sp)

/* 140(sp)      "saved" k0 was dummy garbage anyway */
/* 144(sp)      "saved" k1 was dummy garbage anyway */

```

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 89

```

lw gp, 148(sp) /* restore gp */
/* 152(sp)      stack pointer - below */
lw s8, 156(sp) /* restore s8 */
lw k0, 160(sp) /* fetch exception return PC into k0 */

lw sp, 152(sp) /* fetch saved sp (must be last) */

/* done */
jr k0           /* jump back */
rfe            /* in delay slot */
.end common_exception_return

```

Note again that only k0, k1 have been trashed

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 90