


# System Calls

# Contents

- A high-level view of System Calls
  - Mostly from the user's perspective
    - From textbook (section 1.6)
- A look at the R3000
  - A brief overview
  - Mostly focused on exception handling
    - From "Hardware Guide" on class web site
  - Allow me to provide "real" examples of theory
- System Call implementation
  - Case Study: OS/161 system call handling

# Operating System System Calls



# System Calls

- Can be viewed as special procedure calls
  - Provides for a controlled entry into the kernel
  - While in kernel, they perform a privileged operation
  - Returns to original caller with the result
- The system call interface represents the abstract machine provided by the operating system.

# A Brief Overview of Classes System Calls

- From the user's perspective
  - Process Management
  - File I/O
  - Directories management
  - Some other selected Calls
  - There are many more
    - On Linux, see `man syscalls` for a list

# Some System Calls For Process Management

Process management	
Call	Description
<code>pid = fork( )</code>	Create a child process identical to the parent
<code>pid = waitpid(pid, &amp;statloc, options)</code>	Wait for a child to terminate
<code>s = execve(name, argv, environp)</code>	Replace a process' core image
<code>exit(status)</code>	Terminate process execution and return status

## Some System Calls For File Management

File management	
Call	Description
fd = open(file, how, ...)	Open a file for reading, writing or both
s = close(fd)	Close an open file
n = read(fd, buffer, nbytes)	Read data from a file into a buffer
n = write(fd, buffer, nbytes)	Write data from a buffer into a file
position = lseek(fd, offset, whence)	Move the file pointer
s = stat(name, &buf)	Get a file's status information

## Some System Calls For Directory Management

Directory and file system management	
Call	Description
s = mkdir(name, mode)	Create a new directory
s = rmdir(name)	Remove an empty directory
s = link(name1, name2)	Create a new entry, name2, pointing to name1
s = unlink(name)	Remove a directory entry
s = mount(special, name, flag)	Mount a file system
s = umount(special)	Unmount a file system

## Some System Calls For Miscellaneous Tasks

Miscellaneous	
Call	Description
s = chdir(dirname)	Change the working directory
s = chmod(name, mode)	Change a file's protection bits
s = kill(pid, signal)	Send a signal to a process
seconds = time(&seconds)	Get the elapsed time since Jan. 1, 1970

## System Calls

- A stripped down shell:

```

while (TRUE) {
    type_prompt( );
    read_command (command, parameters)
}

if (fork() != 0) {
    /* Parent code */
    waitpid( -1, &status, 0);
} else {
    /* Child code */
    execve (command, parameters, 0);
}
    
```

## System Calls

UNIX	Win32	Description
fork	CreateProcess	Create a new process
waitpid	WaitForSingleObject	Can wait for a process to exit
execve	(none)	CreateProcess + fork + execve
exit	ExitProcess	Terminate execution
open	CreateFile	Create a file or open an existing file
close	CloseHandle	Close a file
read	ReadFile	Read data from a file
write	WriteFile	Write data to a file
lseek	SetFilePointer	Move the file pointer
stat	GetFileAttributesEx	Get various file attributes
mkdir	CreateDirectory	Create a new directory
rmdir	RemoveDirectory	Remove an empty directory
link	(none)	Win32 does not support links
unlink	DeleteFile	Destroy an existing file
mount	(none)	Win32 does not support mount
umount	(none)	Win32 does not support mount
chdir	SetCurrentDirectory	Change the current working directory
chmod	(none)	Win32 does not support security (although NT does)
kill	(none)	Win32 does not support signals
time	GetLocalTime	Get the current time

### Some Win32 API calls

## The MIPS R2000/R3000

- Before looking at system call mechanics in some detail, we need a basic understanding of the MIPS R3000

## MIPS R3000

- RISC architecture – 5 stage pipeline




Figure 1.1. MIPS 5 stage pipeline

## MIPS R3000

- Load/store architecture
  - No instructions that operate on memory except load and store
  - Simple load/stores to/from memory from/to registers
    - Store word: `sw r4, (r5)`
      - Store contents of r4 in memory using address contained in register r5
    - Load word: `lw r3, (r7)`
      - Load contents of memory into r3 using address contained in r7
      - Delay of one instruction after load before data available in destination register
        - Must always an instruction between a load from memory and the subsequent use of the register.
- `lw, sw, lb, sb, lh, sh, ...`

## MIPS R3000


- Arithmetic and logical operations are register to register operations
  - E.g., `add r3, r2, r1`
  - No arithmetic operations on memory
- Example
  - `add r3, r2, r1`  $\Rightarrow r3 = r2 + r1$
- Some other instructions
  - `add, sub, and, or, xor, sll, srl`

## MIPS R3000

- All instructions are encoded in 32-bit
- Some instructions have *immediate* operands
  - Immediate values are constants encoded in the instruction itself
  - Only 16-bit value
  - Examples
    - Add Immediate: `addi r2, r1, 2048`
      - $\Rightarrow r2 = r1 + 2048$
    - Load Immediate: `li r2, 1234`
      - $\Rightarrow r2 = 1234$

## MIPS Registers

- User-mode accessible registers
  - 32 general purpose registers
    - r0 hardwired to zero
    - r31 the *link* register for jump-and-link (JAL) instruction
  - HI/LO
    - 2 \* 32-bits for multiply and divide
  - PC
    - Not directly visible
    - Modified implicitly by jump and branch instructions



## Branching and Jumping

- Branching and jumping have a *branch delay slot*
  - The instruction following a branch or jump is always executed

```

sw $0, ($3)
j 1f
li $2, 1
:
1: sw $2, ($3)
    
```

## Jump and Link

- JAL is used to implement function calls
  - r31 = PC+8
- Jump Register (JR) is used to return from function call

```

      :
      | jal 1f
      | nop
      | lw $4, ($6)
      | :
      | 1: sw $2, ($3)
      | :
      | jr $31
      | nop
      :
  
```

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 19

## R3000 Address Space Layout

- kuseg:
  - 2 gigabytes
  - TLB translated (mapped)
  - Cacheable
  - user-mode and kernel mode accessible
  - Page size is 4K

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 0x00000000

## R3000 Address Space Layout

- kseg0:
  - 512 megabytes
  - Fixed translation window to physical memory
    - 0x80000000 - 0x9ffffff virtual = 0x00000000 - 0x1ffffff physical
    - TLB not used
  - Cacheable
  - Only kernel-mode accessible
  - Usually where the kernel code is placed

THE UNIVERSITY OF NEW SOUTH WALES Physical Memory 0x00000000

## R3000 Address Space Layout

- kseg1:
  - 512 megabytes
  - Fixed translation window to physical memory
    - 0xa0000000 - 0xbffffff virtual = 0x00000000 - 0x1ffffff physical
    - TLB not used
  - NOT cacheable
  - Only kernel-mode accessible
  - Where devices are accessed (and boot ROM)

THE UNIVERSITY OF NEW SOUTH WALES Physical Memory 0x00000000

## R3000 Address Space Layout

- kseg2:
  - 1024 megabytes
  - TLB translated (mapped)
  - Cacheable
  - Only kernel-mode accessible

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 0x00000000

## System161 Aside

- System/161 simulates an R3000 without a cache.
  - You don't need to worry about cache issues with programming OS161 running on System/161

THE UNIVERSITY OF NEW SOUTH WALES COMP3231 04s1 24

## Coprocessor 0

- The processor control registers are located in CP0
  - Exception management registers
  - Translation management registers
- CP0 is manipulated using mtc0 (move to) and mfc0 (move from) instructions
  - mtc0/mfc0 are only accessible in kernel mode.

## CP0 Registers

- Exception Management
    - c0\_cause
      - Cause of the recent exception
    - c0\_status
      - Current status of the CPU
    - c0\_epc
      - Address of the instruction that caused the exception
        - Note the BD bit in c0\_cause
    - c0\_badvaddr
      - Address accessed that caused the exception
  - Miscellaneous
    - c0\_prId
      - Processor Identifier
  - Memory Management
    - c0\_index
    - c0\_random
    - c0\_entryhi
    - c0\_entrylo
    - c0\_context
- More about these later in course

## c0\_status




Figure 3.2. Fields in status register (SR)

- CU0-3
  - Enable access to coprocessors (1 = enable)
    - CU0 never enabled for user mode
      - Always accessible in kernel-mode regardless of setting
    - CU1 is floating point unit (if present, FPU not in sys161)
    - CU2-3 reserved

## c0\_status




Figure 3.2. Fields in status register (SR)

- RE
  - Reverse endian
- BEV
  - Boot exception vectors
    - 1 = use ROM exception vectors
    - 0 = use RAM exception vectors
- TS
  - TLB shutdown (1 = duplicate entry, need a hardware reset)

## c0\_status




Figure 3.2. Fields in status register (SR)

- PE
  - Parity error in cache
- CM
  - Cache management
- PZ
  - Cache parity zero
- SwC
  - Access instruction cache as data
- IsC
  - Isolate data cache
- For practical purposes, you can ignore these bits

## c0\_status




Figure 3.2. Fields in status register (SR)

- IM
  - Individual interrupt mask bits
    - 6 external
    - 2 software
- KU
  - 0 = kernel
  - 1 = user mode
- IE
  - 0 = all interrupts masked
  - 1 = interrupts enable
    - Mask determined via IM bits
- c, p, o = current, previous, old

### c0\_cause

31	30	29	28	27	16	15	8	7	6	2	1	0
BD	0	CE	0	IP	0	ExcCode	0					

**Figure 3.3. Fields in the Cause register**

- **BD**
  - If set, the instruction that caused the exception was in a branch delay slot
- **CE**
  - Coprocessor error
    - Attempt to access disabled Copro.
- **IP**
  - Interrupts pending
    - 8 bits indicating current state of interrupt lines
- **ExcCode**
  - The code number of the exception taken

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
31

### Exception Codes

ExcCode Value	Mnemonic	Description
0	Int	Interrupt
1	Mod	"TLB modification"
2	TLBL	"TLB load/TLB store"
3	TLBS	
4	AdEL	Address error (on load/I-fetch or store respectively). Either an attempt to access outside kuseg when in user mode, or an attempt to read a word or half-word at a misaligned address.
5	AdES	

**Table 3.2. ExcCode values: different kinds of exceptions**

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
32

### Exception Codes

ExcCode Value	Mnemonic	Description
6	IBE	Bus error (instruction fetch or data load, respectively). External hardware has signalled an error of some kind; proper exception handling is system-dependent. The R30xx family CPUs can't take a bus error on a store; the write buffer would make such an exception "imprecise".
7	DBE	
8	Syscall	Generated unconditionally by a <i>syscall</i> instruction.
9	Bp	Breakpoint - a <i>break</i> instruction.
10	RI	"reserved instruction"
11	CpU	"Co-Processor unusable"
12	Ov	"arithmetic overflow". Note that "unsigned" versions of instructions (e.g. <i>addu</i> ) never cause this exception.
13-31	-	reserved. Some are already defined for MIPS CPUs such as the R6000 and R4xxx

**Table 3.2. ExcCode values: different kinds of exceptions**

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
33

### c0\_epc

- **The Exception Program Counter**
  - The address of where to restart execution after handling the exception or interrupt
  - BD-bit in *c0\_cause* is used on rare occasions when one needs to identify the actual exception-causing instruction
  - Example
    - Assume `sw r3, (r4)` causes a page fault exception

```

nop
sw r3 (r4)
nop

```

↑ *c0\_epc*  
BD = 0

```

nop
j printf
sw r3 (r4)
nop

```

↑ *c0\_epc*  
BD = 1

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
34

### c0\_badvaddr

- The address access that caused the exception
  - Set if exception is
    - MMU related
    - Access to kernel space from user-mode
    - Unaligned memory access
      - 4-byte words must be aligned on a 4-byte boundary

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
35


### Exception Vectors

Program address	"segment"	Physical Address	Description
0x8000 0000	kseg0	0x0000 0000	TLB miss on <i>kuseg</i> reference only.
0x8000 0080	kseg0	0x0000 0080	All other exceptions.
0xbfc0 0100	kseg1	0x1fe0 0100	Uncached alternative <i>kuseg</i> TLB miss entry point (used if <i>SR</i> bit BEV set).
0xbfc0 0180	kseg1	0x1fe0 0180	Uncached alternative for all other exceptions, used if <i>SR</i> bit BEV set).
0xbfc0 0000	kseg1	0x1fe0 0000	The "reset exception".

**Table 4.1. Reset and exception entry points (vectors) for R30xx family**

THE UNIVERSITY OF NEW SOUTH WALES
COMP3231 04s1
36


## Hardware exception handling



COMP3231 04s1

37


## Hardware exception handling



COMP3231 04s1

38


## Hardware exception handling



COMP3231 04s1

39


## Hardware exception handling



COMP3231 04s1



40

## Hardware exception handling



41

## Hardware exception handling




COMP3231 04s1

42


## Returning from an exception

- For now, lets ignore
  - how the exception is actually handled
  - how user-level registers are preserved
- Let's simply look at how we return from the exception


## Returning from an exception




## Returning from an exception



## Returning from an exception




## Returning from an exception




## Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().




## Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().



## Function Stack Frames

- Each function call allocates a new stack frame for local variables, the return address, previous frame pointer etc.
- Example: assume f1() calls f2(), which calls f3().



## Software Register Conventions

- Given 32 registers, which registers are used for
  - Local variables?
  - Argument passing?
  - Function call results?
  - Stack Pointer?




## Software Register Conventions

Reg No	Name	Used for
0	zero	Always returns 0
1	at	(assembler temporary) Reserved for use by assembler
2-3	v0-v1	Value (except FP) returned by subroutine
4-7	a0-a3	(arguments) First four parameters for a subroutine
8-15	t0-t7	(temporaries) subroutines may use without saving
24-25	t8-t9	
16-23	s0-s7	Subroutine "register variables": a subroutine which will write one of these must save the old value and restore it before it exits, so the calling routine sees their values preserved.
26-27	k0-k1	Reserved for use by interrupt/trap handler - may change under your feet
28	gp	global pointer - some runtime systems maintain this to give easy access to (some) "static" or "extern" variables.
29	sp	stack pointer
30	s8/tp	9th register variable. Subroutines which need one can use this as a "frame pointer".
31	ra	Return address for subroutine



## Stack Fram

- MIPS calling convention for gcc
  - Args 1-4 have space reserved for them



## Example Code

```
main ()
{
    int i;

    i =
    sixargs(1,2,3,4,5,6);
}

int sixargs(int a, int b,
            int c, int d, int e,
            int f)
{
    return a + b + c + d
        + e + f;
}
```



```

0040011c <main>:
40011c: 27bdfdf8      addiu sp,sp,-40
400120: afbf0024      sw ra,36(sp)
400124: afbe0020      sw s8,32(sp)
400128: 03a0f021      move s8,sp
40012c: 24020005      li v0,5
400130: afa20010      sw v0,16(sp)
400134: 24020006      li v0,6
400138: afa20014      sw v0,20(sp)
40013c: 24040001      li a0,1
400140: 24050002      li a1,2
400144: 24060003      li a2,3
400148: 0c10002c      jal 4000b0 <sixargs>
40014c: 24070004      li a3,4
400150: afc20018      sw v0,24(s8)
400154: 03c0e821      move sp,s8
400158: 8fbf0024      lw ra,36(sp)
40015c: 8fbe0020      lw s8,32(sp)
400160: 03e00008      jr ra
400164: 27bd0028      addiu sp,sp,40
...

```

```

004000b0 <sixargs>:
4000b0: 27bdfdf8      addiu sp,sp,-8
4000b4: afbe0000      sw s8,0(sp)
4000b8: 03a0f021      move s8,sp
4000bc: afc40008      sw a0,8(s8)
4000c0: afc5000c      sw a1,12(s8)
4000c4: afc60010      sw a2,16(s8)
4000c8: afc70014      sw a3,20(s8)
4000cc: 8fc30008      lw v1,8(s8)
4000d0: 8fc2000c      lw v0,12(s8)
4000d4: 00000000      nop
4000d8: 00621021      addu v0,v1,v0
4000dc: 8fc30010      lw v1,16(s8)
4000e0: 00000000      nop
4000e4: 00431021      addu v0,v0,v1
4000e8: 8fc30014      lw v1,20(s8)
4000ec: 00000000      nop
4000f0: 00431021      addu v0,v0,v1
4000f4: 8fc30018      lw v1,24(s8)
4000f8: 00000000      nop

```

```

4000fc: 00431021      addu v0,v0,v1
400100: 8fc3001c      lw v1,28(s8)
400104: 00000000      nop
400108: 00431021      addu v0,v0,v1
40010c: 03c0e821      move sp,s8
400110: 8fbf0000      lw s8,0(sp)
400114: 03e00008      jr ra
400118: 27bd0008      addiu sp,sp,8

```

## System Calls

Continued

## User and Kernel Execution

- Simplistically, execution state consists of
  - Registers, processor mode, PC, SP
- User applications and the kernel have their own execution state.
- System call mechanism safely transfers from user execution to kernel execution and back.

## System Call Mechanism in Principle

- Processor mode
  - Switched from user-mode to kernel-mode
    - Switched back when returning to user mode
- SP
  - User-level SP is saved and a kernel SP is initialised
    - User-level SP restored when returning to user-mode
- PC
  - User-level PC is saved and PC set to kernel entry point
    - User-level PC restored when returning to user-level
  - Kernel entry via the designated entry point must be strictly enforced


## System Call Mechanism in Principle

- Registers
  - Set at user-level to indicate system call type and its arguments
    - A convention between applications and the kernel
  - Some registers are preserved at user-level or kernel-level in order to restart user-level execution
    - Depends on language calling convention etc.
  - Result of system call placed in registers when returning to user-level
    - Another convention

## Why do we need system calls?

- Why not simply jump into the kernel via a function call????
  - Function calls do not
    - Change from user to kernel mode
      - and eventually back again
    - Restrict possible entry points to secure locations

## Steps in Making a System Call



There are 11 steps in making the system call read (fd, buffer, nbytes)

## MIPS System Calls


- System calls are invoked via a *syscall* instruction.
  - The *syscall* instruction causes an exception and transfers control to the general exception handler
  - A convention (an agreement between the kernel and applications) is required as to how user-level software indicates
    - Which system call is required
    - Where its arguments are
    - Where the result should go

## OS/161 Systems Calls

- OS/161 uses the following conventions
  - Arguments are passed and returned via the normal C function calling convention
  - Additionally
    - Reg v0 contains the system call number
    - On return, reg a3 contains
      - 0: if success, v0 contains successful result
      - not 0: if failure, v0 has the errno.
        - » v0 stored in errno
        - » -1 returned in v0

# CAUTION

- Seriously low-level code follows
- This code is not for the faint hearted



## User-Level System Call Walk Through

```
int read(int filehandle, void *buffer, size_t size)
```

- Three arguments, one return value
- Code fragment calling the read function

```
400124: 02602021  move  a0,s3
400128: 27a50010  addiu  a1,sp,16
40012c: 0c1001a3  jal   40068c <read>
400130: 24060400  li    a2,1024
400134: 00408021  move  s0,v0
400138: 1a000016  blez  s0,400194 <docat+0x94>
```

- Args are loaded, return value is tested



## The read() syscall function part 1

```
0040068c <read>:
```

```
40068c: 08100190  j    400640 <__syscall>
400690: 24020005  li   v0,5
```

- Appropriate registers are preserved
  - Arguments (a0-a3), return address (ra), etc.
- The syscall number (5) is loaded into v0
- Jump (not jump and link) to the common syscall routine



## The read() syscall function part 2

Generate a syscall exception

```
00400640 <__syscall>:
400640: 0000000c  syscall
400644: 10e00005  beqz  a3,40065c <__syscall+0x1c>
400648: 00000000  nop
40064c: 3c011000  lui   at,0x1000
400650: ac220000  sw   v0,0(at)
400654: 2403ffff  li   v1,-1
400658: 2402ffff  li   v0,-1
40065c: 03e00008  jr   ra
400660: 00000000  nop
```



## The read() syscall function part 2

Test success, if yes, branch to return from function

```
00400640 <__syscall>:
400640: 0000000c  syscall
400644: 10e00005  beqz  a3,40065c <__syscall+0x1c>
400648: 00000000  nop
40064c: 3c011000  lui   at,0x1000
400650: ac220000  sw   v0,0(at)
400654: 2403ffff  li   v1,-1
400658: 2402ffff  li   v0,-1
40065c: 03e00008  jr   ra
400660: 00000000  nop
```



## The read() syscall function part 2

If failure, store code in *errno*

```
00400640 <__syscall>:
400640: 0000000c  syscall
400644: 10e00005  beqz  a3,40065c
400648: 00000000  nop
40064c: 3c011000  lui   at,0x1000
400650: ac220000  sw   v0,0(at)
400654: 2403ffff  li   v1,-1
400658: 2402ffff  li   v0,-1
40065c: 03e00008  jr   ra
400660: 00000000  nop
```



## The read() syscall function part 2

Set read() result to -1

```
00400640 <__syscall>:
400640: 0000000c  syscall
400644: 10e00005  beqz  a3,40065c
400648: 00000000  nop
40064c: 3c011000  lui   at,0x1000
400650: ac220000  sw   v0,0(at)
400654: 2403ffff  li   v1,-1
400658: 2402ffff  li   v0,-1
40065c: 03e00008  jr   ra
400660: 00000000  nop
```



## The read() syscall function part 2

```

00400640 <_syscall>:
400640: 0000000c syscall
400644: 10e00005 beqz a3,40065c
400648: 00000000 nop
40064c: 3c011000 lui at,0x1000
400650: ac220000 sw v0,0(at)
400654: 2403ffff li v1,-1
400658: 2402ffff li v0,-1
40065c: 03e00008 jx ra
400660: 00000000 nop
    
```

Return to location after where read() was called



## Summary

- From the caller's perspective, the read() system call behaves like a normal function call
  - It preserves the calling convention of the language
- However, the actual function implements its own convention by agreement with the kernel
  - Our OS/161 example assumes the kernel preserves appropriate registers(s0-s8, sp, gp, ra).
- Most languages have similar *support libraries* that interface with the operating system.



## System Calls - Kernel Side

- Things left to do
  - Change to kernel stack
  - Preserve registers by saving to memory (the stack)
  - Leave saved registers somewhere accessible to
    - Read arguments
    - Store return values
  - Do the "read()"
  - Restore registers
  - Switch back to user stack
  - Return to application



```

exception:
    move k1, sp          /* Save previous stack pointer in k1 */
    mfc0 k0, c0_status  /* Get status register */
    andi k0, k0, CST_Kup /* Check the we-were-in-user-mode bit */
    beq k0, $0, 1f /* If clear, from kernel, already have stack */
    nop                 /* delay slot */

    /* Coming from user mode - load kernel stack into sp */
    la k0, curkstack    /* get address of "curkstack" */
    lw sp, 0(k0)        /* get its value */
    nop                 /* delay slot for the load */

1:
    mfc0 k0, c0_cause /* Now, load the exception cause. */
    j common_exception /* Skip to common code */
    nop
    
```

Note k0, k1 registers available for kernel use



```

exception:
    move k1, sp          /* Save previous stack pointer in k1 */
    mfc0 k0, c0_status  /* Get status register */
    andi k0, k0, CST_Kup /* Check the we-were-in-user-mode bit */
    beq k0, $0, 1f /* If clear, from kernel, already have stack */
    nop                 /* delay slot */

    /* Coming from user mode - load kernel stack into sp */
    la k0, curkstack    /* get address of "curkstack" */
    lw sp, 0(k0)        /* get its value */
    nop                 /* delay slot for the load */

1:
    mfc0 k0, c0_cause /* Now, load the exception cause. */
    j common_exception /* Skip to common code */
    nop                 /* delay slot */
    
```



```

common_exception:
    /*
     * At this point:
     *   Interrupts are off. (The processor did this for us.)
     *   k0 contains the exception cause value.
     *   k1 contains the old stack pointer.
     *   sp points into the kernel stack.
     *   All other registers are untouched.
     */

    /*
     * Allocate stack space for 37 words to hold the trap frame,
     * plus four more words for a minimal argument block.
     */
    addi sp, sp, -164
    
```





## Now we arrive in the 'C' kernel

```

/*
 * General trap (exception) handling function for mips.
 * This is called by the assembly-language exception handler once
 * the trapframe has been set up.
 */
void
mips_trap(struct trapframe *tf)
{
    u_int32_t code, isutlb, iskern;
    int savespl;

    /* The trap frame is supposed to be 37 registers long. */
    assert(sizeof(struct trapframe)==(37*4));

    /* Save the value of curspl, which belongs to the old context. */
    savespl = curspl;

    /* Right now, interrupts should be off. */
    curspl = SPL_HIGH;

```



## What happens next?

- The kernel deals with whatever caused the exception
  - Syscall
  - Interrupt
  - Page fault
  - It potentially modifies the *trapframe*, etc
    - E.g., Store return code in v0, zero in a3
- 'mips\_trap' eventually returns



exception\_return:

```

/*      16(sp)      no need to restore tf_vaddr */
lw t0, 20(sp)      /* load status register value into t0 */
nop                /* load delay slot */
mtc0 t0, c0_status /* store it back to coprocessor 0 */
/*      24(sp)      no need to restore tf_cause */

/* restore special registers */
lw t1, 28(sp)
lw t0, 32(sp)
mtlo t1
mthi t0

/* load the general registers */
lw ra, 36(sp)

lw AT, 40(sp)
lw v0, 44(sp)
lw v1, 48(sp)
lw a0, 52(sp)
lw a1, 56(sp)
lw a2, 60(sp)
lw a3, 64(sp)

```



```

lw t0, 68(sp)
lw t1, 72(sp)
lw t2, 76(sp)
lw t3, 80(sp)
lw t4, 84(sp)
lw t5, 88(sp)
lw t6, 92(sp)
lw t7, 96(sp)
lw s0, 100(sp)
lw s1, 104(sp)
lw s2, 108(sp)
lw s3, 112(sp)
lw s4, 116(sp)
lw s5, 120(sp)
lw s6, 124(sp)
lw s7, 128(sp)
lw t8, 132(sp)
lw t9, 136(sp)

/*      140(sp)      "saved" k0 was dummy garbage anyway */
/*      144(sp)      "saved" k1 was dummy garbage anyway */

```



```

lw gp, 148(sp)      /* restore gp */
/*      152(sp)      stack pointer - below */
lw s8, 156(sp)     /* restore s8 */
lw k0, 160(sp)     /* fetch exception return PC into k0 */

lw sp, 152(sp)     /* fetch saved sp (must be last) */

/* done */
jr k0                /* jump back */
rfe                 /* in delay slot */
.end common_exception

```

Note again that only  
k0, k1 have been  
trashed

